Error Correction

Why Error Correction is Harder

If we had reliable check bits we could use them to narrow down the position of the error

- Then correction would be easy

But error could be in the check bits as well as the data bits

- Data might even be correct!

Intuition for Error Correcting Code

Assume a code with a Hamming distance of at least 3
- Need ≥3 bit errors to change a valid codeword into another
- Single bit errors will be closest to a unique valid codeword

If we assume errors are only 1 bit, we can correct mapping an error to the closest valid codeword
- Works for d errors if HD ≥ 2d + 1

Intuition (2)

Valid codeword

Error codeword

Intuition (3)

Single bit error from A

Valid codeword

Three bit errors to get to B

Error codeword

Hamming Code

Method for constructing a code with a distance of 3

- Uses n = $2^k - k - 1$, e.g., n=4, k=3
- Put check bits in positions p that are powers of 2, starting with position 1
- N-th check bit is parity of bit positions with n-th LSBit is same as p's

Plus an easy way to correct [soon]

Hamming Code (2)

- Example: data=0101, 3 check bits
  - 7 bit code, check bit positions 1, 2, 4
  - Check 1 covers positions 1, 3, 5, 7 (LSB is 1)
  - Check 2 covers positions 2, 3, 6, 7 (2nd LSB is 1)
  - Check 4 covers positions 4, 5, 6, 7 (3rd LSB is 1)

$$0 \quad 1 \quad 0 \quad 0 \quad 1 \quad 0 \quad 1$$
$$1 \quad 2 \quad 3 \quad 4 \quad 5 \quad 6 \quad 7$$

p_1= 0+1+1 = 0, p_2= 0+0+1 = 1, p_4= 1+0+1 = 0

CSE 461 University of Washington

Hamming Code (3)

- To decode:
  - Recompute check bits (with parity sum including the check bit)
  - Arrange as a binary number
  - Value (syndrome) tells error position
  - Value of zero means no error
  - Otherwise, flip bit to correct

Hamming Code (5)

- Example, continued

$\longrightarrow$ $\underline{0}$ $\underline{1}$ 0 $\underline{0}$ 1 0 1

 1 2 3 4 5 6 7

p_1= p_2=

p_4=

Syndrome =

Data =

Hamming Code (6)

- Example, continued

$\longrightarrow$ <u>0</u> <u>1</u> 0 <u>0</u> 1 0 1

1 2 3 4 5 6 7

p_1= 0+0+1+1 = 0, p_2= 1+0+0+1 = 0,
p_4= 0+1+0+1 = 0

Syndrome = 000, no error
Data = 0 1 0 1

Hamming Code (7)

- Example, continued

$\longrightarrow$ <u>0</u> <u>1</u> 0 <u>0</u> 1 1 1

1 2 3 4 5 6 7

$p_1=$ $p_2=$

$p_4=$

Syndrome =

Data =

Hamming Code (8)

- Example, continued

⟶ 0 1 0 0 1 1 1

1 2 3 4 5 6 7

p_1 = 0+0+1+1 = 0, p_2 = 1+0+1+1 = 1,

p_4 = 0+1+1+1 = 1

Syndrome = 1 1 0, flip position 6

Data = 0 1 0 1 (correct after flip!)

Hamming Code (9)

- Example: bad message 0100111
  - 7 bit code, check bit positions 1, 2, 4
  - Check 1 covers positions 1, 3, 5, 7
  - Check 2 covers positions 2, 3, 6, 7
  - Check 4 covers positions 4, 5, 6, 7

$$0 \quad 1 \quad 0 \quad 0 \quad 1 \quad 1 \quad 1 \quad \longrightarrow$$

1 2 3 4 5 6 7

$p_1 = 0+0+1+1 = 0, \quad p_2 = 1+0+1+1 = 1, \quad p_4 = 0+1+1+1 = 1$

Hamming Code (10)

- Example: bad message 0100111
  - 7 bit code, check bit positions 1, 2, 4
  - Check 1 covers positions 1, 3, 5, 7
  - Check 2 covers positions 2, 3, 6, 7
  - Check 4 covers positions 4, 5, 6, 7

$$0\ 1\ 0\ 0\ 1\ 1\ 1 \longrightarrow$$

$$1\ \ 2\ \ 3\ \ 4\ \ 5\ \ 6\ \ 7$$

$p_1 = 0+0+1+1 = 0, \quad p_2 = 1+0+1+1 = 1, \quad p_4 = 0+1+1+1 = 1$

Other Error Correction Codes

- Real codes are more involved than Hamming

- E.g., Convolutional codes (§3.2.3)
  - Take a stream of data and output a mix of the input bits
  - Makes each output bit less fragile
  - Decode using Viterbi algorithm (uses bit confidence values)

Detection vs. Correction

Example:
- 1000 bit messages with a <u>bit error rate</u> (<u>BER</u>) of 1 in 10000

Which is better will depend on the pattern of errors

Detection vs. Correction (2)

Assume bit errors are random
- Messages have 0 or maybe 1 error (1/10 of the time)

Error correction:
- Need ~10 check bits per message
- Overhead:
  - 10 bits per message

Error detection:
- Need ~1 check bits per message plus 1000 bit retransmission
- Overhead:
  - 101 bits per message

Detection vs. Correction (3)

Assume errors come in bursts of 100
- Only 1 or 2 messages in 1000 have significant (multi-bit) errors

Error correction:
- Need >>100 check bits per message
- Overhead:
  - >> 100 bpm

Error detection:
- Need 32 check bits per message plus 1000 bit resend 2/1000 of the time
- Overhead:
  - 34 bits per message

Detection vs. Correction (4)

- Error correction:
  - Needed when errors are expected
  - Or when no time for retransmission

- Error detection:
  - More efficient when errors are not expected
  - And when errors are large when they do occur

Error Correction in Practice

- Heavily used in physical layer
  - Used for demanding links like 802.11, DVB, WiMAX, power-line, …
  - Convolutional codes widely used in practice

- Error detection (w/ retransmission) is used in the link layer and above for residual errors

- Correction also used in the application layer
  - Called Forward Error Correction (FEC)
  - Normally with an erasure error model
  - E.g., Reed-Solomon (CDs, DVDs, etc.)

Error Correction in Practice (2)

- Everywhere! It is a key issue
  - Different layers contribute differently

Application
Transport
Network
Link
Physical

Recover actions
(correctness)

↑

Mask errors
(performance optimization)