15. Parametric surfaces

Reading

Required:

• Watt, 2.1.4, 3.4-3.5.

Optional

- Watt, 3.6.
- Bartels, Beatty, and Barsky. An Introduction to Splines for use in Computer Graphics and Geometric Modeling, 1987.

2

Mathematical surface representations

- ◆ Explicit *z*=*f*(*x*,*y*) (a.k.a., a "height field")
 - what if the curve isn't a function, like a sphere?



- Implicit g(x,y,z) = 0
- Parametric S(u,v)=(x(u,v),y(u,v),z(u,v))
 - For the sphere:

$$x(u,v) = r \cos 2\pi v \sin \pi u$$
$$y(u,v) = r \sin 2\pi v \sin \pi u$$

 $z(u,v) = r \cos \pi u$

As with curves, we'll focus on parametric surfaces.

Surfaces of revolution

Idea: rotate a 2D profile curve around an axis.

What kinds of shapes can you model this way?

Constructing surfaces of revolution

Given: A curve C(u) in the xy-plane:

$$C(u) = \begin{bmatrix} c_x(u) \\ c_y(u) \\ 0 \\ 1 \end{bmatrix}$$

Let $R_{\nu}(\theta)$ be a rotation about the x-axis.


Find: A surface S(u,v) which is C(u) rotated about the *x*-axis.

Solution:

General sweep surfaces

The **surface of revolution** is a special case of a **swept surface**.

Idea: Trace out surface S(u,v) by moving a **profile curve** C(u) along a **trajectory curve** T(v).



More specifically:

- ◆ Suppose that *C*(*u*) lies in an (*x_c*, *y_c*) coordinate system with origin *O_c*.
- For every point along T(v), lay C(u) so that O_c coincides with T(v).

5

6


Orientation

The big issue:

• How to orient C(u) as it moves along T(v)?

Here are two options:


1. **Fixed** (or **static**): Just translate O_c along T(v).



- 2. Moving. Use the **Frenet frame** of T(v).
 - Allows smoothly varying orientation.
 - Permits surfaces of revolution, for example.

Frenet frames

Motivation: Given a curve T(v), we want to attach a smoothly varying coordinate system.



To get a 3D coordinate system, we need 3 independent direction vectors.

 $\mathbf{t}(v) = \text{normalize}[T'(v)]$

 $\mathbf{b}(v) = \text{normalize}[T'(v) \times T''(v)]$


 $\mathbf{n}(v) = \mathbf{b}(v) \times \mathbf{t}(v)$

As we move along T(v), the Frenet frame (t,b,n) varies smoothly.

Frenet swept surfaces

Orient the profile curve C(u) using the Frenet frame of the trajectory T(v):

- Put C(u) in the **normal plane**.
- Place O_c on T(v).
- Align x_c for C(u) with **b**.
- Align y_c for C(u) with -**n**.




If T(v) is a circle, you get a surface of revolution exactly!


What happens at inflection points, i.e., where curvature goes to zero?

Variations

Several variations are possible:


- Scale C(u) as it moves, possibly using length of T(v) as a scale factor.
- Morph C(u) into some other curve $\tilde{C}(u)$ as it moves along T(v).
- ***** ...





10

Tensor product Bézier surfaces




Given a grid of control points V_{ij} , forming a **control net**, contruct a surface S(u,v) by:

- treating rows of V (the matrix consisting of the V_{ij}) as control points for curves $V_0(u), ..., V_n(u)$.
- treating $V_0(u),...,V_n(u)$ as control points for a curve parameterized by v.

Tensor product Bézier surfaces, cont.

Let's walk through the steps:



Which control points are interpolated by the surface?

11

Matrix form of Bézier curves and surfaces

Recall that Bézier curves can be written in terms of the Bernstein polynomials:

$$Q(u) = \sum_{i=0}^{n} V_i b_i(u)$$

They can also be written in a matrix form:

$$Q^{T}(u) = \begin{bmatrix} u^{3} & u^{2} & u & 1 \end{bmatrix} \begin{bmatrix} -1 & 3 & -3 & 1 \\ 3 & -6 & 3 & 0 \\ -3 & 3 & 0 & 0 \\ 1 & 0 & 0 & 0 \end{bmatrix} \begin{bmatrix} V_{0}^{T} \\ V_{1}^{T} \\ V_{2}^{T} \\ V_{3}^{T} \end{bmatrix}$$

$$= \begin{bmatrix} u^3 & u^2 & u & 1 \end{bmatrix} \mathbf{M}_{Bezier} \mathbf{V}_{curve}$$

Tensor product surfaces can be written out similarly:


$$S(u,v) = \sum_{i=0}^{n} \sum_{j=0}^{n} V_{ij} b_{i}(u) b_{j}(v)$$

$$= \begin{bmatrix} u^3 & u^2 & u & 1 \end{bmatrix} \mathbf{M}_{\text{Bézier}} \mathbf{V}_{\text{surface}} \mathbf{M}_{\text{Bézier}}^{\mathsf{T}} \begin{bmatrix} v^3 \\ v^2 \\ v \\ 1 \end{bmatrix}$$

13

Tensor product B-spline surfaces


As with spline curves, we can piece together a sequence of Bézier surfaces to make a spline surface. If we enforce C^2 continuity and local control, we get B-spline curves:





- treat rows of *B* as control points to generate Bézier control points in *u*.
- treat Bézier control points in u as B-spline control points in v.
- treat B-spline control points in v to generate Bézier control points in u.


14

Tensor product B-spline surfaces, cont.









Which B-spline control points are interpolated by the surface?

Matrix form of B-spline surfaces

Recall that we could write a matrix form for generating Bezier control points from B-spline control points for curves:

$$\begin{bmatrix} V_0^T \\ V_1^T \\ V_2^T \\ V_3^T \end{bmatrix} = \frac{1}{6} \begin{bmatrix} 1 & 4 & 1 & 0 \\ 0 & 4 & 2 & 0 \\ 0 & 2 & 4 & 0 \\ 0 & 1 & 4 & 1 \end{bmatrix} \begin{bmatrix} B_0^T \\ B_1^T \\ B_2^T \\ B_3^T \end{bmatrix}$$


$$V_{curve} = M_{B-spline}B_{curve}$$

We can arrive at a similar form for tensor product B-spline surfaces:

$$\mathbf{V}_{\text{surface}} = \mathbf{M}_{\text{B-spline}} \mathbf{B}_{\text{surface}} \mathbf{M}_{\text{B-spline}}^{\text{T}}$$

Tensor product B-splines, cont.

Another example:




Trimmed NURBS surfaces

Uniform B-spline surfaces are a special case of NURBS surfaces.

Sometimes, we want to have control over which parts of a NURBS surface get drawn.

For example:



We can do this by **trimming** the *u-v* domain.

- Define a closed curve in the *u-v* domain (a **trim curve**)
- Do not draw the surface points inside of this curve.

It's really hard to maintain continuity in these regions, especially while animating.